

dot_emacs

fichier.emacs

```
(custom-set-variables
;; custom-set-variables was added by Custom.
;; If you edit it by hand, you could mess it up, so be careful.
;; Your init file should contain only one such instance.
;; If there is more than one, they won't work right.

;; st pour afficher elinks:
'(browse-url-elinks-wrapper (quote ("st" "-e")))
'(compose-mail-user-agent-warnings nil)

;; confirmer pour quitter:
'(confirm-kill-emacs (quote y-or-n-p))
'(custom-enabled-themes (quote (molokai)))
'(custom-safe-themes
  (quote
    ("fe20c1ea61a2836a5cea69963865b5b8df8c480ccaf3f11ad7f2e1f543f6c274"
    "c3c0a3702e1d6c0373a0f6a557788dfd49ec9e66e753fb24493579859c8e95ab"
    default)))
'(gnus-directory "~/news/")
'(imap-default-user "blablapeople")
'(imap-store-password t)
'(inhibit-startup-screen t)
'(message-directory "~/mail/")
'(read-mail-command (quote gnus))
'(send-mail-function (quote smtpmail-send-it))
'(smtpmail-smtp-server "server.net")
'(smtpmail-smtp-service 465)
'(smtpmail-smtp-user "blablapeople")
'(smtpmail-stream-type (quote ssl))
'(user-full-name "blabla")
'(user-mail-address "blabla")

;;;;;;;;;;;;;;
;; sogal dot emacs ;;
;;;;;;;;;;;;;;

;; support de la souris dans le terminal
;; (require 'mouse)
;; (xterm-mouse-mode t)
;; (global-set-key (kbd "<mouse-5>") 'scroll-up-line)
;; (global-set-key (kbd "<mouse-4>") 'scroll-down-line)

;; affichage des numéros de ligne (et de colonnes en bas)
(global-linum-mode t)
(setq linum-format "%d ")
```

```

(setq column-number-mode t)

;; custom quote level colorizing in mail-mode:
(add-hook 'mail-mode-hook
  (lambda ()
    (font-lock-add-keywords nil
      '(("^[\t]*>[\t]*>[\t]*>.*$"
        (0 'mail-multiply-quoted-text-face))
        ("^[\t]*>[\t]*>.*$"
        (0 'mail-double-quoted-text-face))))))

;; restriction des lignes à 80 caractères :
(setq-default fill-column 80)
;; pour le mode mail :
(add-hook 'mail-mode-hook 'turn-on-auto-fill)
;; et le mode python :
(add-hook 'python-mode-hook
  (lambda ()
    (turn-on-auto-fill)
    (linum-mode)))

;; PO Mode Line Wrapping:
(defun po-wrap ()
  "Filter current po-mode buffer through `msgcat' tool to wrap all
lines."
  (interactive)
  (if (eq major-mode 'po-mode)
    (let ((tmp-file (make-temp-file "po-wrap."))
          (tmp-buf (generate-new-buffer "*temp*")))
      (unwind-protect
        (progn
          (write-region (point-min) (point-max) tmp-file nil 1)
          (if (zerop
              (call-process
               "msgcat" nil tmp-buf t (shell-quote-argument tmp-file)))
              (let ((saved (point))
                    (inhibit-read-only t))
                (delete-region (point-min) (point-max))
                (insert-buffer tmp-buf)
                (goto-char (min saved (point-max))))
              (with-current-buffer tmp-buf
                (error (buffer-string))))))
          (kill-buffer tmp-buf)
          (delete-file tmp-file))))))

;; démarrer emacs dans mutt en mode mail
(add-to-list 'auto-mode-alist '("/mutt" . mail-mode))

;; affecter replace-string:
(global-set-key (kbd "C-x C-r") 'replace-string)

```

```
;; auto-completion avec la touche TAB:
(global-set-key (kbd "<backtab>") 'dabbrev-expand)

;; définir l'emplacement des sauvegardes (backup):
(setq backup-directory-alist '((" " . "~/.emacs.d/backups/")))

;; affecter ispell-buffer à une touche:
(global-set-key (kbd "M-f") 'ispell-buffer)

;; affecter next-buffer à Super-Page Down:
(global-set-key (kbd "<s-next>") 'next-buffer)
;; et affecter previous-buffer à Super-Page UP:
(global-set-key (kbd "<s-prior>") 'previous-buffer)

;; configuration courriel
(setq gnus-select-method
      '(nnimap "mail"
                (nnimap-address "mail")
                (nnimap-server-port "imaps")
                (nnimap-stream ssl)))

;; ajout de la transparence (totale, cadre compris) :
(set-frame-parameter (selected-frame) 'alpha '(98 70))
(add-to-list 'default-frame-alist '(alpha 98 70))

;; fonction et raccourcis de toggle de la transparence :
(eval-when-compile (require 'cl))
(defun toggle-transparency ()
  (interactive)
  (if (/=
        (cadr (frame-parameter nil 'alpha))
        100)
      (set-frame-parameter nil 'alpha '(100 100))
      (set-frame-parameter nil 'alpha '(98 70)))
  (global-set-key (kbd "C-c t") 'toggle-transparency)
  (custom-set-faces
   ;; custom-set-faces was added by Custom.
   ;; If you edit it by hand, you could mess it up, so be careful.
   ;; Your init file should contain only one such instance.
   ;; If there is more than one, they won't work right.
  )
```

From:
<http://debian-facile.org/> - Documentation - Wiki

Permanent link:
<http://debian-facile.org/utilisateurs:sogal:config:emacs>

Last update: **11/11/2015 15:14**



